



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

1 Type of device

- Field device / signal processing device
- Monitoring- / operation system / hand held terminal etc.
- Modem / interface

Manufacturer : Endress+Hauser
 Device : Liquistation
 Type : CSF48, CSF34
 Previous software version : 1.03.01

How can the previous software version number be identified:

- (a) With standard Fieldbus communication
- (b) with FieldCare/DTM
- (c) Display

2 Software

New software version : 1.04.00

Description of the modification in comparison with the predecessor version:

Samper - New Features, Enhancements & Improvements

- Start screen with direct link to edit the sampling program
- After power reset the sampling program continues
- Inline sampler with sampling volumes 10 ml ... 1 l
All other sampler: minimal volume 20 ml
- Sub-program active selectable for binary output or relay
- Optimized sampling volume for vacuum sampling with capacitive media detection
- Bottle change according edited time interval allow empty bottles now
- Bottle change according time zone configuration

New Features/Modules:

- New extension module: 2x digital input & 2x digital output ("DIO") featuring:
 - Input: Measuring range switch for conductivity
 - Input: External Hold
 - Input: triggering of a cleaning cycle via an external signal
 - Input: PID-controller enable/disable e.g. via CCA250-Proximity switch
 - Input: usable as "analog input" for Pulse Frequency Modulated (PFM) input signals
 - Output: static, usable comparable to a relay, e.g. for signaling diagnostic states, limit switches, etc.
 - Output: dynamic, usable comparable to a wearless "analog output" with Pulse Frequency Modulated (PFM) signals (e.g. for dosing pump control)
- Status of Relays, digital inputs and digital outputs can be displayed also in user definable



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

measurements screens

- Key lock (by long pressing the Navigator) with optional password protection
- The printing of the device configuration via FieldCare is optimized
- PID-Controller: now supports also disturbance feed forward control allowing e.g. flow proportional dosing via 0/4..20mA, digital fieldbus or the new digital inputs.
- Mathematics: pH out of conductivity value is now also calculable basing on LiOH (according the new "VBG Powertech group guideline" for the power & energy industry)

Enhancements & Improvements:

- For Configuration with Siemens Simatic the higher slot numbers were moved to slot numbers lower than 34
- Offset Icon - Harmonization across all parameters to not display the offset icon anymore
Note: Offset Icon will only be displayed at pH and ORP
- Human Machine Interface (HMI): Translation of all new menu items (including the items of the release 3a) into all available languages

ISE: New Features, Enhancements & Improvements

- Re-arranged and simplified calibration menu implemented
- Calibration of any two parameters in one sequence is possible (except pH/temperature)
- Slot numbers in the menus are replaced by parameter name
- A user defined ISE type can be chosen
- At the end of the standard addition the concentration of the original sample is displayed.

pH/ ORP: New Features, Enhancements & Improvements

- Support of CPSx6 combined pH/ORP electrodes
- Icon for automatic, manual or medium compensation (ATC/ MTC/ MED) same as with conductivity are available

Conductivity: New Features, Enhancements & Improvements

- The raw value in resistivity mode at the unit " μS " is available with three decimal places
- Extension of ISO Temperature compensation table by "Water ISO7888 (20°C)"
- Integration of new & enhancing existing concentration tables

Dissolved Oxygen: New Features, Enhancements & Improvements

- All units now available with three decimal places (e.g. 0.003 mg/l)
- A warning message for zero current now also for negative values (before: just+1nA, now: +/- 1nA)
- After successful calibration the new slope and in addition the used calibration pressure value is now shown. User can now cross check if the calibration pressure of the extended setup/calibration setting is used.

Turbidity, Nitrate, SAC: New Features, Enhancements & Improvements

- Turbidity: auto ranging can be switched on or off. In the Off-mode, the units mg/l or g/l or % can be chosen. In the On-mode, the system selects the units mg/l or g/l automatically.
- Turbidity, SAC, Nitrate: A Dataset can be saved also after editing its name
- Turbidity, SAC, Nitrate: When copying datasets, it is now indicated what will be used as source and as target.
- Turbidity, SAC, Nitrate: Values for Offsets can now be entered for a wide range. The range is



Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

not defined anymore by the sensor.

3 Compatibility

Is the operating tool compatible with the installed device software?

- Yes
 No, description:

Remark: The PROFIBUS-GSD file is fully compatible.
 For device configuration a new EDD file or a new DTM are necessary.

Is a software update generally recommended?

- Yes, reason:

The software update can be performed by means of ...

- SD card

- No, reason:

Update only necessary if functional enhancements are desired

4 Instruction manual

Is a new instruction manual necessary due to the modification of the software?

- Yes
 No

Which manual corresponds to the new software:

Device	Communication options	Manual Marking
CSF48, CSF34	All	BA00443CDE.pdf
		BA00463CDE.pdf
		BA00464CDE.pdf
		BA00467CDE.pdf
		Liquistation Commissioning
		Liquistation Maintenance & Diagnostics
		Liquistation Operation & Setting
		Liquistation Calibration

The new instruction manuals can be referred in Internet:

<http://www.endress.com> - area „DOWNLOAD“
 - declaration of the device and kind of manual



Level



Pressure



Flow



Temperature



Liquid
Analysis



Registration



Systems
Components



Services



Solutions

Manufacturer Information

for users regarding software updates
(following the NAMUR recommendation 53)

5 Price

Change in price of device in comparison with the predecessor version?

- Yes, new list price and update costs (without installation) are enclosed
 No